

(for version 11.83)

Carriage Return or C-m	RET
Tabular or C-i	TAB
Linefeed or C-j	LFD

Run a command on the master file	C-c C-c
Run a command on the buffer	C-c C-b
Run a command on the region	C-c C-r
Fix the region	C-c C-t C-r
Kill job	C-c C-k
Recenter output buffer	C-c C-l
Next error in T <sub>E</sub> X/L <sup>A</sup> T <sub>E</sub> X session	C-c ‘
Toggle debug of wonderful boxes	C-c C-w
View output file	C-c C-v

<code>TeX</code>	<code>*TeX</code>
<code>LaTeX</code>	<code>*LaTeX</code>
<code>ConTeXt</code> (once)	<code>*ConTeXt</code>
<code>ConTeXt</code> Full	<code>*ConTeXt Full</code>
<code>Makeinfo</code>	<code>*Makeinfo</code>
<code>Makeinfo</code> with HTML output	<code>*Makeinfo HTML</code>
Appropriate previewer	<code>View</code>
Print the output	<code>Print</code>
<code>BibTeX</code>	<code>BibTeX</code>
<code>MakeIndex</code>	<code>Index</code>
<code>LaCheck</code>	<code>Check</code>
<code>Make</code> (PostScript) File	<code>File</code>
<code>IsPELL</code>	<code>Spell</code>

$\Omega$ mode	C-c C-t C-o
PDF/DVI mode	C-c C-t C-p
Stop on errors (Interactive mode)	C-c C-t C-i
Use Source Specials for viewer control	C-c C-t C-s

Read AUCTeX manual	C-c TAB
Math Mode	C-c ~
Reset Buffer	C-c C-n
Reset AUCTeX	C-u C-c C-n

Save Document	C-c C-d
Switch to master file or active buffer	C-c ^
Query for a master file	C-c _

Insert Section	C-c C-s
Insert L <sup>A</sup> T <sub>E</sub> X environment	C-c C-e
Insert item	C-c LFD
Insert item (alias)	M-RET
Close L <sup>A</sup> T <sub>E</sub> X environment	C-c ]
Insert T <sub>E</sub> X macro \{ }	C-c C-m
Insert double brace	C-c {
Complete T <sub>E</sub> X macro	M-TAB
Smart “quote”	"
Smart “dollar”	\$

Insert <b>bold</b> text	C-c C-f C-b
Insert <i>italics</i> text	C-c C-f C-i
Insert <i>roman</i> text	C-c C-f C-r
Insert <i>emphasized</i> text	C-c C-f C-e
Insert <b>typewriter</b> text	C-c C-f C-t
Insert <i>slanted</i> text	C-c C-f C-s
Insert SMALL CAPS text	C-c C-f C-c
Delete font	C-c C-f C-d
Replace font	C-u C-c C-f ⟨key⟩

Indent current line	TAB
Indent next line	LFD
Format a paragraph	M-q
Format a region	C-c C-q C-r
Format a section	C-c C-q C-s
Format an environment	C-c C-q C-e
Mark an environment	C-c .
Mark a section	C-c *
Comment or uncomment region	C-c ;
Comment or uncomment paragraph	C-c %

Permission is granted to make and distribute copies of this card provided the copyright notice and this permission notice are preserved on all copies.

$\alpha$	(\alpha)	a	$v$	(\upsilon)	u
$\beta$	(\beta)	b	$\phi$	(\phi)	f
$\gamma$	(\gamma)	g	$\chi$	(\chi)	q
$\delta$	(\delta)	d	$\psi$	(\psi)	y
$\epsilon$	(\epsilon)	e	$\omega$	(\omega)	w
$\zeta$	(\zeta)	z	$\Delta$	(\Delta)	D
$\eta$	(\eta)	h	$\Gamma$	(\Gamma)	G
$\theta$	(\theta)	j	$\Theta$	(\Theta)	Q
$\kappa$	(\kappa)	k	$\Lambda$	(\Lambda)	L
$\lambda$	(\lambda)	l	$\Xi$	(\Xi)	X
$\mu$	(\mu)	m	$\Pi$	(\Pi)	P
$\nu$	(\nu)	n	$\Sigma$	(\Sigma)	S
$\xi$	(\xi)	x	$\Upsilon$	(\Upsilon)	U
$\pi$	(\pi)	p	$\Phi$	(\Phi)	F
$\rho$	(\rho)	r	$\Psi$	(\Psi)	Y
$\sigma$	(\sigma)	s	$\Omega$	(\Omega)	W
$\tau$	(\tau)	t			

$\rightarrow$	(\rightarrow)	C-f	$\supseteq$	(\supseteqeq)	]
$\leftarrow$	(\leftarrow)	C-b	$\emptyset$	(\emptysetset)	0
$\uparrow$	(\uparrow)	C-p	$\backslash$	(\setminus)	\
$\downarrow$	(\downarrow)	C-n	$\cup$	(\cup)	+
$\leq$	(\leq)	<	$\cap$	(\cap)	-
$\geq$	(\geq)	>	$\langle$	(\langle)	(
$\tilde{x}$	(\tilde)	~	$\rangle$	(\rangle)	)
$\nabla$	(\nabla)	N	exp	(\exp)	C-e
$\infty$	(\infty)	I	sin	(\sin)	C-s
$\forall$	(\forall)	A	cos	(\cos)	C-c
$\exists$	(\exists)	E	sup	(\sup)	C-^
/	(\not)	/	inf	(\inf)	C-_
$\in$	(\in)	i	det	(\det)	C-d
$\times$	(\times)	*	lim	(\lim)	C-l
$\cdot$	(\cdot)	.	tan	(\tan)	C-t
$\subset$	(\subset)	{	$\hat{x}$	(\hat)	^
$\supset$	(\supset)	}	$\vee$	(\vee)	
$\subseteq$	(\subseteq)	[	$\wedge$	(\wedge)	&

cal letters	c <letter>
-------------	------------

# preview-latex

## Activation

preview-latex is part of AUCTeX. If it is active, you should see an entry “Preview” in the menu bar when editing L<sup>A</sup>T<sub>E</sub>X files. If you have a “LaTeX”, but no “Preview” menu, add the following to your .emacs file:

```
(load "preview-latex.el" nil t t)
```

## Usage and keybindings

preview-latex operation only affects the display of the buffer, not its contents. It runs only on demand, using the target DVI or PDF files in the process. The first command in the following list (also on the toolbar button) will (as applicable) repreview an active region or a single modified preview, toggle the visibility of an unmodified preview or generate previews for a surrounding buffer area up to the next preview.

Preview at point	C-c C-p C-p
Preview environment	C-c C-p C-e
Preview region	C-c C-p C-r
Preview buffer	C-c C-p C-b
Preview document	C-c C-p C-d
Remove previews at point	C-c C-p C-c C-d
Remove previews from region	C-c C-p C-c C-r
Remove previews from buffer	C-c C-p C-c C-b
Remove previews from document	C-c C-p C-c C-d
Cache preamble	C-c C-p C-f
Switch off preamble cache	C-c C-p C-c C-f
Read Texinfo manual	C-c C-p TAB
Copy region as MML	C-c C-p C-w

The last keysequence will copy a region with previews into the kill buffer in a form fit for sending in Emacs’ message-mode.

## Customization within Emacs

You can use M-x customize-variable RET or the “Preview/Customize” menu for customization. Worthwhile settings:

If you have dvipng available:	
Set to dvipng	preview-image-type
Keep counter values when regenerating single previews:	
Set to t	preview-preserve-counters
Cache/Don’t cache preamble without query (preamble caching is done using mylatex.ltx and might not always work. Use the appropriate key sequences for overriding the following setting):	
Set to t/nil	preview-auto-cache-preamble

# Customization from L<sup>A</sup>T<sub>E</sub>X

Customization is done in the document preamble (you need to load preview.sty explicitly) or in prauctex.cfg (which should load the system prauctex.cfg first). Commands:

Preview macro	\PreviewMacro[{(args)}]{(macro)}
Preview env	\PreviewEnvironment[{(args)}]{(env)}
Skip macro	\PreviewMacro*[{(args)}]{(macro)}
Skip env	\PreviewEnvironment*[{(args)}]{(env)}

Diverting material from float environments	
Snarf stuff	\PreviewSnarfEnvironment[{(args)}]{(env)}
Values to be used within (args):	
Optional argument	[]
Mandatory argument	{}
Optional star	*
Conditionals	?(token){(if found)}{(if not found)}
Skip next token	-
Transformation	#{(macro args)}{(replacement)}

More options and explanations can be found in preview.dvi or the Texinfo manual.

## Folding Source Display

Toggle folding mode	C-c C-o C-f
Hide all items in buffer	C-c C-o C-b
Hide all items in region	C-c C-o C-r
Hide all items in paragraph	C-c C-o C-p
Hide current macro	C-c C-o C-m
Hide current environment	C-c C-o C-e
Show all items in buffer	C-c C-o b
Show all items in region	C-c C-o r
Show all items in paragraph	C-c C-o p
Show current item	C-c C-o i
Hide or show current item	C-c C-o C-o

# RefTeX

## Activation

RefTeX is part of [X]Emacs. To activate and make it interact with AUCTeX, insert the following lines in .emacs.

```
(add-hook 'latex-mode-hook 'turn-on-reftex)
(add-hook 'LaTeX-mode-hook 'turn-on-reftex)
(setq reftex-plug-into-auctex t)
```

## Table of Contents

The table of contents is a structured view of the entire document. It contains the sections, and optionally labels, index entries, and file boundaries.

Show the table of contents <sup>1</sup>	C-c =
Recenter *toc* buffer to here <sup>1</sup>	C-c -

## Crossreferences, Citations, Index

Insert unique label <sup>1</sup>	C-c (
Reference a label <sup>1</sup>	C-c )
Insert citation with key selection	C-c [
... prompt for optional arguments	C-u C-c [
Index word at point with default macro	C-c /
Insert an index entry	C-c <
Add word to index phrases	C-c \
Visit index phrases buffer	C-c
Compile and display index	C-c >
View cross reference <sup>1</sup>	C-c &
View cross reference with mouse	S-mouse-2
View cross reference from BibTeX file	C-c &

## Standard keys in special buffers

RefTeX’s special buffers have many active keys. The common ones are:

Display summary of active keys	?
Select this item	RET
Rescan the document	r
Display location in other window	SPC
Follow mode	f

## Multifile actions

Since RefTeX scans the entire (multifile) document, it can provide commands that act on all files of a document. Check the Ref->Global Actions menu for these commands.

## Variables

To tell reftex about your own macro definitions, customize the variables

```
reftex-label-alist
reftex-section-lecels
reftex-index-macros
reftex-cite-format
```

<sup>1</sup> An argument of C-u triggers a document scan first. This can be necessary if file content and RefTeX’s knowledge are no longer consistent.